VirusGEN[®] LV Transfection Kit

Protocol for MIR 6760

Quick Reference Protocol, SDS and Certificate of Analysis available at mirusbio.com/6760

INTRODUCTION

Lentivirus is an enveloped, single-stranded RNA virus from the *Retroviridae* family capable of infecting both dividing and non-dividing cells. Combined with an efficient host-genome integration mechanism and the ability to pseudotype the virus, this capability makes recombinant lentivirus a central gene delivery tool for robust and stable transgene expression in target cells.

The *Trans*IT-VirusGEN[®] Transfection Reagent enables the generation of high titer lentivirus in HEK 293 cell types. The VirusGEN[®] LV Transfection Kit further enhances the performance of *Trans*IT-VirusGEN[®] Transfection Reagent in adherent and suspension HEK 293 cells through inclusion of the proprietary VirusGEN[®] LV Complex Formation Solution and VirusGEN[®] LV Enhancer. The *Trans*IT-VirusGEN[®] LV Transfection Kit is ideal for generating high titer lentivirus preparations to accelerate research and development.

SPECIFICATIONS

Storage	Store <i>Trans</i> IT-VirusGEN [®] Reagent at -10 to -30°C, tightly capped. Store VirusGEN [®] LV Enhancer at 2 to 10°C. Store VirusGEN [®] LV Complex Formation Solution at 2 to 10°C.			
Stability / Guarantee	6 months from the date of purchase, when properly stored and handled.			

!

Warm *Trans*IT-VirusGEN[®] Reagent, VirusGEN[®] LV Complex Formation Solution and VirusGEN[®] LV Enhancer to room temperature before each use. Mix gently.

MATERIALS

Materials Supplied

The VirusGEN[®] LV Transfection Kit (MIR 6760) is supplied in the following format.

Product No.	Component	Quantity
MIR 6702A	TransIT-VirusGEN® Transfection Reagent	2 × 1.5 ml
MIR 6761A	VirusGEN [®] LV Enhancer	1 × 100 ml
MIR 6762A	VirusGEN [®] LV Complex Formation Solution	1 × 100 ml

For Materials Required but Not Supplied, See Protocol Sections:

- (I) Lentivirus Generation in Adherent HEK 293T Cell Cultures
- (II) Lentivirus Generation in Suspension HEK 293 Cell Cultures
- (III) Lentivirus Transduction and Titering Protocol Using GFP Reporter Virus

For Research Use Only



BEFORE YOU START:

Important Tips for Optimal Lentivirus Production

Mirus recommends using HEK 293T/17 cells (ATCC Cat. No. CRL-11268) or Expi293FTM Cells (Gibco Cat. No. A14527) for high titer lentivirus production in adherent or suspension HEK 293 cultures, respectively. The suggestions below yield high efficiency plasmid DNA transfection using the VirusGEN[®] LV Transfection Kit.

- Cell density (% confluence) at transfection. The recommended cell density for adherent HEK 293T/17 cells is 80-95% confluence at the time of transfection. The recommended cell density for suspension Expi293FTM cells is 4 × 10⁶ cells/ml. Passage cells 18-24 hours before transfection to ensure that cells are actively dividing and reach the appropriate density at time of transfection.
- DNA purity. Use highly purified, sterile, endotoxin-free and contaminant-free DNA for transfection. Plasmid DNA preparations that have an A_{260/280} absorbance ratio of 1.8-2.0 are desirable. DNA prepared using miniprep kits is not recommended as it might contain high levels of endotoxin. We recommend using MiraCLEAN[®] Endotoxin Removal Kit (MIR 5900) to remove endotoxin from your DNA preparation.
- Lentivirus packaging and transfer plasmids. The *Trans*IT-VirusGEN[®] Reagent was optimized using a lentivirus packaging vector pre-mix. If using individual packaging plasmids, we recommend a starting ratio of 4 μg *gag-pol* vector, 1 μg *rev* vector and 1 μg VSV-G vector. Premix the packaging plasmids with an equal amount of the transfer vector (e.g. 6 μg) to maintain a 1:1 (wt:wt) ratio of packaging to transfer plasmids.
- Ratio of *Trans*IT-VirusGEN[®] to DNA. Determine the optimal *Trans*IT-VirusGEN[®] Reagent:DNA ratio for each cell type by varying the amount of reagent from 2-4 µl per 1 µg total DNA. Refer to **Tables 1** and **2** for recommended starting conditions based on cell culture vessel size.
- **Complex formation conditions.** Prepare *Trans*IT-VirusGEN[®] Reagent:DNA complexes in VirusGEN[®] LV Complex Formation Solution. We recommend forming complexes in a volume that is 10% of the total culture volume. If forming complexes in a smaller or larger volume, complex formation time may need to be shortened or extended.
- Cell culture conditions. Culture cells in the appropriate medium, with or without serum (e.g. DMEM + 10% FBS + 10 mM HEPES pH 7.4 for adherent 293T cultures; Expi293TM Expression Medium for suspension 293 cultures). Ensure cells are ≥ 95% viable by trypan blue exclusion and doubling every 24 hours. After transfection, there is no need to perform a medium change to remove the transfection complexes.
- VirusGEN[®] LV Enhancer Addition. We recommend adding the VirusGEN[®] LV Enhancer at a volume that is 10% of the total culture volume, approximately 18-24 hours post-transfection. Addition at an earlier time may result in lower titer.
- **Presence of antibiotics.** Antibiotics inhibit transfection complex formation and should be excluded from the complex formation step. Transfection complexes can be added directly to cells growing in complete culture medium containing serum and low levels of antibiotics (0.1-1X final concentration of penicillin/streptomycin mixture).
- Media change post-transfection. A media change is not required and could be detrimental to virus titers; therefore, we do not recommend a media change post-transfection.
- **Post-transfection incubation time.** The optimal incubation time for harvesting high titer lentivirus is 48 hours. Minimal amounts of functional lentivirus are produced during the period of 48-72 hours post-transfection.



Premix packaging and transfer plasmids together prior to adding to the complex formation medium.

Do not use serum or antibiotics in the media during transfection complex formation.

Transfection complexes can be added directly to cells cultured in growth media +/- serum and up to 0.1-1X antibiotics.



SECTION I: Lentivirus Generation in Adherent HEK 293T Cell Cultures

The following procedure describes plasmid DNA transfections for lentivirus generation in adherent HEK 293T cell types in a <u>6-well plate format</u>. The surface areas of other culture vessels are different, and transfections must be scaled accordingly. Appropriately increase or decrease the amounts of VirusGEN[®] LV Complex Formation Solution, *Trans*IT-VirusGEN[®] Reagent, total plasmid DNA, complete culture medium and VirusGEN[®] LV Enhancer based on the size of the cell culture vessel (refer to **Table 1** below).

Culture vessel	6-well plate	10-cm dish	T75 flask	T175 flask	Corning® 2-STACK	Corning® 5-STACK
Surface area	9.6 cm^2	59 cm ²	75 cm^2	175 cm^2	1272 cm^2	3180 cm ²
Complete growth medium	2.0 ml	10 ml	15 ml	35 ml	260 ml	650 ml
VirusGEN [®] LV Complex Formation Solution	200 µl	1.0 ml	1.5 ml	3.5 ml	26 ml	65 ml
Transfer DNA (1 µg/µl stock)	1.0 µl	5 µl	7.5 μl	17.5 µl	134 µl	325 µl
Packaging DNA Premix (1 µg/µl stock)	1.0 µl	5 µl	7.5 µl	17.5 µl	134 µl	325 µl
TransIT-VirusGEN® Reagent	6 µl	30 µl	45 µl	105 µl	804 µl	1.95 ml
NOTE: Add VirusGEN [®] LV Enhancer <u>18-24 hours post-transfection</u> .						
VirusGEN [®] LV Enhancer	200 µl	1.0 ml	1.5 ml	3.5 ml	26 ml	65 ml

Table 1. Recommended starting conditions for VirusGEN[®] LV Transfection Kit

Surfac

Surface areas are based on Falcon plates, dishes and flasks, and Corning CellSTACK® Culture Chambers. Volumes are per well (or dish) for a given culture vessel. For vessels not listed in this table, volumes of PBS, total DNA and *Trans*IT-VirusGEN[®] Reagent can typically be scaled according to surface area (cm²).

Materials Required but Not Supplied

- HEK 293T cells (e.g. HEK 293T/17 cells, ATCC Cat. No. CRL-11268)
- Complete culture medium (e.g. DMEM + 10% FBS + 10 mM HEPES pH 7.4)
- Nucleic acid (packaging plasmids and transfer vector with gene of interest)
- Phosphate Buffered Saline (PBS) (e.g. MilliporeSigma, Cat. No. D8537)
- 0.45 µm PVDF filter (e.g. Millipore Cat. No. SE1M003M00 or SLHV033RS)
- Reporter assay as required





Transient Plasmid Transfection Protocol per Well of a 6-Well Plate

A. Plate cells

- 1. Approximately 18-24 hours before transfection, plate cells in 2.0 ml complete growth medium per well in a 6-well plate. A starting cell density of $4.0 6.0 \times 10^5$ cells/ml is recommended. Cultures should be 80-95% confluent at the time of transfection (see representative image at right).
- 2. Incubate cell cultures at 37°C in 5% CO₂ overnight.

B. Prepare *Trans*IT-VirusGEN[®]:DNA complexes (immediately before transfection)

- 1. Warm *Trans*IT-VirusGEN[®] Transfection Reagent to room temperature and vortex gently before using.
- 2. Place 200 µl VirusGEN[®] LV Complex Formation Solution in a sterile tube.
- 3. In a separate sterile tube, combine the packaging plasmid premix (or individual plasmids) and transfer plasmid encoding the gene of interest (GOI). Mix thoroughly.
- Transfer 2 μg (1 μg packaging plasmid mix + 1 μg transfer plasmid) of the DNA prepared in Step B.3 to the tube containing VirusGEN[®] LV Complex Formation Solution. Mix completely.
- 5. Add 6 μl *Trans*IT-VirusGEN[®] Reagent to the diluted DNA mixture. Mix completely by inversion or vortexing. Do NOT agitate Reagent:DNA complexes again after this initial mixing.

NOTE: This is a 3:1 mixture of transfection reagent to total DNA, which can be further optimized for lentivirus production using *Trans*IT-VirusGEN[®] Reagent.

6. Incubate at room temperature for 15-60 minutes to allow transfection complexes to form.

C. Distribute the complexes to cells in complete growth medium

- 1. Add the *Trans*IT-VirusGEN[®] Reagent:DNA complexes (prepared in Step B) drop-wise to different areas of the wells.
- 2. Gently rock the culture vessel back-and-forth and from side-to-side to evenly distribute the *Trans*IT-VirusGEN[®] Reagent:DNA complexes.
- 3. Incubate cultures for <u>18-24 hours</u> before addition of VirusGEN[®] LV Enhancer.

D. Add VirusGEN[®] LV Enhancer to transfected cell culture

- After 18-24 hours post-transfection, add 200 μl of VirusGEN[®] LV Enhancer to the culture vessel containing the transfected cell culture. Gently rock the culture vessel to mix completely.
- 2. Incubate cultures for an additional <u>24-30 hours</u>, i.e. 48 hours post-transfection, before harvesting lentivirus.

E. Harvest and storage of lentivirus

- Harvest cell supernatant containing recombinant lentivirus particles. NOTE: If cells detach during harvest, centrifuge cells at 300 × g for 5 minutes and retain the virus-containing supernatant.
- 2. Filter virus-containing supernatant through a 0.45 µm PVDF filter to remove any cells.
- 3. Immediately flash freeze aliquots of lentivirus in cryogenic tubes and store at -80°C.



Divide cultured cells 18-24 hours before transfection to ensure active cell division at the time of transfection.

Representative image of ~80% confluent 293T/17 cells:





There is no need to change culture medium after transfection.

Transfection complexes, visualized as small particles, are sometimes observed following transfection. The complexes are not toxic to cells and do not affect transfection efficiency or transgene expression.

Page 4 of 11



SECTION II: Lentivirus Generation in Suspension HEK 293 Cell Cultures

The following procedure describes plasmid DNA transfections for lentivirus generation in 125 ml Erlenmeyer shake flasks using <u>25 ml</u> of complete growth medium. If using alternate cell culture vessels, increase or decrease the amounts of VirusGEN[®] LV Complex Formation Solution, *Trans*IT-VirusGEN[®] Reagent, total plasmid DNA and VirusGEN[®] LV Enhancer based on the **volume of complete growth medium** to be used. To calculate the required reagent quantities based on the recommended starting conditions and total culture volume, refer to the calculation worksheet in **Table 2** (below).

Starting conditions per milliliter of complete growth medium						
	Per 1 ml			Total culture	Pagant quantities	
			volume		Reagent quantities	
VirusGEN [®] LV Complex	0.1	ml	×	ml	= ml	
Formation Solution	0.1	IIII	~	1111	1111	
Transfer plasmid DNA (1 µg/µl stock)	0.5	μl	×	ml	=µl	
Packaging DNA premix (1 µg/µl stock)	0.5	μl	×	ml	=µl	
TransIT-VirusGEN [®] Reagent	3	μl	×	ml	=µl	
NOTE: Add VirusGEN [®] LV Enhancer <u>18-24 hours post-transfection</u> .						
	Per 1 ml		Total culture volume		Reagent quantities	
VirusGEN [®] LV Enhancer	0.1	ml	×	ml	=ml	

Table 2. Scaling worksheet for VirusGEN® LV Transfection Kit

Materials Required but Not Supplied

- Suspension HEK 293 Cells (e.g. Expi293F[™] Cells, Gibco Cat. No. A14527)
- Complete Culture Medium (e.g. Expi293™ Expression Medium, Gibco Cat. No. A1435101)
- Nucleic acid (2nd or 3rd generation packaging plasmids and transfer vector with GOI)
- Phosphate Buffered Saline (PBS) (e.g. MilliporeSigma Cat. No. D8537)
- Erlenmeyer shake flasks (e.g. Corning[®] Cat. No. 431143 or Thomson Cat. No. 931110)
- 50 ml conical tube(s) for virus collection
- 0.45 μm PVDF filter (e.g. Millipore Cat. No. SE1M003M00 or SLHV033RS) Reporter assay as required

Transient Plasmid Transfection Protocol per 25 ml HEK 293 Culture

A. Maintenance of cells

- Passage suspension HEK 293 cells 18-24 hours prior to transfection to ensure that cells are actively dividing at the time of transfection and to obtain a density of 4 - 6 × 10⁶ cells/ml the next day. NOTE: Perform cell counts and evaluate viability daily to ensure that cells are doubling every 24 hours and are ≥ 95% viable by trypan blue exclusion. DO NOT proceed with transfection if cells are not doubling normally or are < 95% viable.
- 2. Incubate cells overnight at appropriate temperature and CO₂ levels (e.g. 37°C, 5-8% CO₂, shaking).



*Trans*IT-VirusGEN[®] Reagent was optimized using a pre-mix of lentivirus packaging vectors. If using individual packaging plasmids, we recommend a starting ratio of 4 µg *gag-pol* vector, 1 µg *rev* vector and 1 µg VSV-G vector. Premix the packaging plasmids with an equal amount of the transfer vector (e.g. 6 µg) to maintain a 1:1 (wt:wt) ratio of packaging to transfer plasmids.



Divide cultured cells 18-24 hours before transfection to ensure that cells are actively dividing at the time of transfection.



B. Prepare *Trans*IT-VirusGEN[®]:DNA complexes (immediately before transfection)

- 1. Immediately prior to transfection, seed cells at a density of 4×10^6 cells/ml into a transfection culture vessel (e.g. 25 ml per 125 ml Erlenmeyer shake flask).
- 2. Warm *Trans*IT-VirusGEN[®] Reagent to room temperature and vortex gently.
- 3. Place 2.5 ml of VirusGEN[®] LV Complex Formation Solution in a sterile tube.
- 4. In a separate sterile tube, combine the packaging plasmid premix (or individual plasmids) and transfer plasmid encoding the gene of interest (GOI). Mix thoroughly.
- Transfer 25 μg (12.5 μg packaging plasmid mix + 12.5 μg transfer plasmid) of the DNA prepared in Step B.4 to the tube containing VirusGEN[®] LV Complex Formation Solution. Mix completely.
- Add 75 μl *Trans*IT-VirusGEN[®] Reagent to the diluted DNA mixture. Mix completely by inversion or vortexing. Do NOT agitate Reagent:DNA complexes again after this initial mixing.

NOTE: This is a 3:1 mixture of transfection reagent to total DNA, which can be further optimized for lentivirus production using *Trans*IT-VirusGEN[®] Reagent.

7. Incubate at room temperature for 15-60 minutes to allow transfection complexes to form.

C. Distribute the complexes to cells in complete growth medium

- 1. Add the *Trans*IT-VirusGEN[®] Reagent:DNA complexes (prepared in Step B) to the flask containing cells. Swirl the flask gently to mix completely.
- 2. Shake flasks on an orbital shaker (125 rpm when using a shaker with a 1.9 cm orbital throw) at appropriate temperature and CO₂ levels (e.g. 37°C, 5-8% CO₂).
- 3. Incubate cultures for <u>18-24 hours</u> before addition of VirusGEN[®] LV Enhancer.

D. Add VirusGEN® LV Enhancer to transfected cell culture

- 1. After 18-24 hours post-transfection, add 2.5 ml of VirusGEN[®] LV Enhancer to the culture vessel containing the transfected cell culture. Swirl the flask gently to mix completely.
- 2. Continue shaking the flasks on an orbital shaker (125 rpm when using a shaker with a 1.9 cm orbital throw) at appropriate temperature and CO₂ levels (e.g. 37°C, 5-8% CO₂).
- 3. Incubate cultures for an additional <u>24-30 hours</u>, i.e. 48 hours post-transfection, before harvesting lentivirus.

E. Harvest and storage of lentivirus

- 1. Following the 48-hour incubation, centrifuge the lentivirus containing culture(s) in sterile conical tube(s) at 300 × g for 5 minutes. DO NOT dispose of supernatant following centrifugation.
- 2. Collect the virus-containing supernatant using a serological pipet into a sterile conical tube. NOTE: If a large batch of the same virus is being produced, the supernatants can be combined.
- Filter the virus-containing supernatant through a 0.45 μm PVDF filter (e.g. Millipore Steriflip-HV, Cat. No. SE1M003M00) to remove any cells.
- 4. Immediately flash-freeze aliquots of lentivirus in cryogenic tubes and store at -80°C.



Do NOT allow the *Trans*IT-VirusGEN[®] Reagent to incubate alone in complex formation solution > 5 min, i.e. if the reagent is pre-diluted, add DNA within 5 min for optimal complex formation.

Do NOT agitate Reagent:DNA complexes after the initial mixing.



There is no need to change culture medium after transfection, unless required by your cell type or culture conditions.

SECTION III: Lentivirus Transduction and Titering Protocol Using GFP Reporter Virus

The following procedure describes transduction of HEK 293T/17 cells grown in a 24-well format with a GFP reporter lentivirus to determine functional lentivirus titers. The number of wells needed for this assay will depend on the number of lentivirus stocks titered and the number of dilutions required for testing per stock (see Step B.4). Testing several dilutions is recommended to accurately determine the functional lentivirus titer.

Materials Required, but Not Supplied

- HEK 293T/17 cells (ATCC Cat. No. CRL-11268)
- Appropriate cell culture medium (e.g. DMEM + 10% FBS + 10 mM HEPES pH 7.4)
- Lentivirus stock(s) expressing GFP reporter
- *Transduce*IT[™] Reagent (10 mg/ml, Mirus Cat. No. MIR 6620) or hexadimethrine bromide (Sigma Cat. No. H9268)
- 24-well tissue culture plate(s)
- 1X PBS and trypsin
- Flow cytometer equipped with a GFP compatible laser

A. Plate cells

- 1. Approximately 18-24 hours before transduction, plate HEK 293T/17 cells in 0.5 ml complete growth medium per well in a 24-well plate. A starting cell density of 2.0×10^5 cells/ml is recommended. Cultures should be $\geq 40\%$ confluent at the time of transduction (see image at right). NOTE: Plate at least two extra wells to trypsinize and count on the day of transduction. An accurate cell count at the time of transduction is critical to determine an accurate functional titer (see B.1).
- 2. Incubate cell cultures at 37°C in 5% CO₂ overnight.

B. Transduce with GFP-encoding recombinant lentivirus

- 1. Trypsinize and count 2 wells of untransduced cells (plated in A.1) to obtain an accurate cell concentration at the time of transduction.
- 2. Dilute *Transduce*ITTM Reagent or hexadimethrine bromide to a working concentration of 16 μg/ml in pre-warmed complete growth medium (e.g. add 16 μl of a 10 mg/ml solution into 10 ml of growth medium).
- 3. Gently remove half of the medium from each well using a P1000 micropipettor.
- 4. Immediately add 250 µl of the *Transduce*ITTM or hexadimethrine bromide working solution to each well. The final concentration should be 8 µg/ml per well. NOTE: If transducing cell types other than HEK 293T/17, the optimal concentration of *Transduce*ITTM or hexadimethrine bromide should be empirically determined.
- 5. Add dilutions of the lentivirus stock to separate wells. Testing several dilutions is recommended to accurately determine functional titer. Guidelines are as follows:
 - For titers expected to be $< 5.0 \times 10^7$ TU/ml, add 1 µl, 3 µl and 5 µl of the lentiviral stock to separate wells.
 - For titers expected to be ≥ 5.0 × 10⁷ TU/ml, dilute the virus stock 10-fold in complete growth media. Add 1 µl, 3 µl and 5 µl of the diluted lentivirus stock to separate wells.
 NOTE: To obtain an accurate titer, it is desirable to have less than 20% GFP positive cells at 72 hours post-transduction. This minimizes counting cells with multiple integration events, which would result in an underestimation of titers.
- 6. Incubate the remaining assay wells at 37°C in 5% CO₂ for 72 hours post-transduction.



Divide cultured cells 18-24 hours before transfection to ensure active cell division at the time of transduction.

Representative image of \geq 40% confluent 293T/17 cells:









C. Cell harvest and analysis

- 1. Gently wash cells with 1X PBS and immediately add 100 μ l of trypsin to each well.
- 2. Incubate the plate at 37°C and closely monitor cell rounding and detachment.
- 3. After cells have detached, add 400 µl of complete growth media to each well to inactivate the trypsin and resuspend the cells.
- 4. Transfer 100 μl of cell suspension from each well to separate wells in a non-treated 96-well plate (or similar culture vessel) that is compatible with your flow cytometer.
- 5. Add 150 μl of complete growth medium to each well to dilute the cells. This is required to obtain accurate flow cytometry results. NOTE: The optimal volume added for dilution may vary depending on the flow cytometer.
- 6. Analyze for GFP expression by flow cytometry.
- 7. Calculate the functional titer of the lentivirus stock using the following equation:

Titer (Transducing Units/ml) = [<u>Number of target cells (Count at time of transduction) × [% GFP positive cells/100]</u> (Volume of lentivirus stock in ml)

Protocol for MIR 6760



TROUBLESHOOTING GUIDE

POOR DNA TRANSFECTION EFFICIENCY				
Problem	Solution			
Incorrect vector sequence	If you do not observe expression of your target insert, verify the sequence of the transfer vector plasmid DNA.			
Suboptimal <i>Trans</i> IT [®] Reagent:DNA ratio	Determine the best <i>Trans</i> IT-VirusGEN [®] Reagent:DNA ratio for each cell type. Titrate the <i>Trans</i> IT-VirusGEN [®] Reagent volume from 2-4 μ l per 1 μ g DNA. Refer to "Before You Start" on Page 2 for recommended starting conditions.			
Suboptimal DNA concentration	Determine the DNA concentration accurately. Use plasmid DNA preps that have an A _{260/280} absorbance ratio of 1.8-2.0.			
	The optimal DNA concentration generally ranges between 0.5-1.5 μ g per 1 ml of culture. Start with 1 μ g DNA per 1 ml of culture. Consider testing different amounts of DNA while scaling the amount of <i>Trans</i> IT-VirusGEN [®] accordingly.			
	Use highly purified, sterile, endotoxin- and contaminant-free DNA for transfection.			
Low-quality plasmid DNA	We recommend using Mirus MiraCLEAN [®] Endotoxin Removal Kit (MIR 5900) for removal of endotoxin from your DNA preparation. Alternatively, use cesium chloride gradient or anion exchange purified DNA which contains levels of endotoxin that do not harm most cells.			
	Do not use DNA prepared using miniprep kits as it might contain high levels of endotoxin.			
Cells not actively dividing at the time of transfection	Divide the culture at least 18-24 hours before transfection to ensure that the cells are actively dividing and reach optimal cell density at time of transfection. DO NOT proceed with transfection if cells are not doubling normally or are $< 95\%$ viable by trypan blue exclusion.			
Transfection incubation time not optimal	Determine the optimal transfection incubation time for each cell type and experiment. Test a range of incubation times (e.g. 48-72 hours). The best post-transfection incubation time for lentivirus production is typically 48 hours.			
	Warm TransIT-VirusGEN [®] Reagent to room temperature and vortex gently before each use.			
<i>Trans</i> IT-VirusGEN [®] was not mixed properly	If <i>Trans</i> IT-VirusGEN [®] Reagent is pre-diluted in complex formation solution, DNA should be added within 5 min. Incubating the <i>Trans</i> IT-VirusGEN [®] Reagent in complex formation solution alone for an extended time results in reduced production of functional virus.			
Disruption of transfection complex formation	After initial mixing of DNA and <i>Trans</i> IT-VirusGEN [®] Reagent, do not agitate Reagent:DNA complexes again, e.g. do not vortex or invert before adding to cultures.			
Precipitate formation during transfection complex formation	During complex formation, scale all reagents according to the scaling tables provided in each section of the protocol, including: serum-free media, <i>Trans</i> IT-VirusGEN [®] Reagent and plasmid DNA.			
	Precipitation may be observed when excess DNA is used during complex formation. This may negatively impact transfection efficiency. To avoid precipitation when using high concentrations of DNA, increase the volume of serum-free medium during complex formation by two-fold.			
Proper experimental controls were not included	To assess delivery efficiency of plasmid DNA, use Mirus <i>Label</i> IT [®] Tracker [™] Intracellular Nucleic Acid Localization Kit to label the target plasmid or use Mirus prelabeled <i>Label</i> IT [®] Plasmid Delivery Controls (please refer to Related Products on Page 11).			
	To verify efficient transfection, use <i>Trans</i> IT-VirusGEN [®] Reagent to deliver a positive control such as a luciferase, beta-galactosidase or green fluorescent protein (GFP) encoding plasmid.			



TROUBLESHOOTING GUIDE continued

HIGH CELLULAR TOXICITY				
Problem	Solution			
Cell density not optimal at time of transfection	High toxicity and cell death may be observed if cells are less than 80% confluent at the time of transfection. For high virus titers using <i>Trans</i> IT-VirusGEN [®] Reagent, ensure that cell cultures are between 80 and 95% confluent (for adherent cell transfections) or approximately 4×10^6 cells/ml (for suspension cell transfections) at the time of transfection.			
Cell morphology has changed	When generating lentivirus, overexpression of the vesicular stomatitis virus (VSV) G protein causes changes in cell morphology and can even result in cell-cell fusion. VirusGEN [®] LV Enhancer may also decrease cell growth. This is normal and does not adversely affect virus titers.			
	Mycoplasma contamination can alter cell morphology and affect transfection efficiency. Check your cells for mycoplasma contamination. Use a fresh frozen stock of cells or use appropriate antibiotics to eliminate mycoplasma.			
	A high or low cell passage number can make cells more sensitive and refractory to transfection. Maintain adherent or suspension HEK 293 cells below passage 30 for optimal recombinant virus production.			
Transfection complexes not evenly distributed after complex addition to cells	Add transfection complexes drop-wise to the cells. Gently rock the dish back-and-forth and from side-to-side to distribute the complexes evenly. Do not swirl or rotate the dish, as this may cause uneven distribution.			
Transfection complexes added to adherent cells cultured in serum-free medium	<i>Trans</i> IT-VirusGEN [®] Transfection Reagent efficiently transfects cells cultured in serum-free medium; however, toxicity may be higher if serum is not present when transfecting adherent cells typically cultured in serum-containing complete media. If toxicity is a problem, consider adding serum to the culture medium.			



RELATED PRODUCTS

- VirusGEN[®] GMP LV Transfection Kit
- VirusGEN[®] SELECT LV Transfection Kit
- VirusGEN[®] GMP AAV Transfection Kit
- VirusGEN[®] SELECT AAV Transfection Kit
- VirusGEN[®] AAV Transfection Kit
- TransIT-VirusGEN® GMP Transfection Reagent
- TransIT-VirusGEN[®] SELECT Transfection Reagent
- TransIT-VirusGEN[®] Transfection Reagent
- *Transduce*ITTM Reagent
- Label IT[®] Plasmid Delivery Controls
- Label IT[®] TrackerTM Intracellular Nucleic Acid Localization Kits
- MiraCLEAN[®] Endotoxin Removal Kits
- Ingenio[®] Electroporation Solution and Kits

For details on the above-mentioned products, visit www.mirusbio.com



Reagent Agent[®] is an online tool designed to help determine the best solution for nucleic acid delivery based on in-house data, customer feedback and citations.

Learn more at: www.mirusbio.com/ra

Contact Mirus Bio for additional information.



Mirus Bio LLC 5602 Research Park Blvd, Ste 210 Madison, WI 53719 Toll-free: 888.530.0801 Direct: 608.441.2852 Fax: 608.441.2849

©1996-2022 All rights reserved. Mirus Bio LLC. All trademarks are the property of their respective owners. For terms and conditions, visit www.mirusbio.com

Rev1 011922

Page 11 of 11